Ndudut Pro — Installation & Quick Start Guide

Version: 1.0.0 | **Product SKU:** AINDPR | **Publisher:** aifadhel (aescripts.com/ndudut-pro)

1. Installation

The easiest way to install and license is by using the aescripts + aeplugins manager app. *To install a trial you can select 'Add Trial' from the 'Account' menu. The manager app automatically delivers the latest tested binary and provisions platform dependencies.*

Manual Standalone Package Installation

- **Windows:** Run NdudutPro_1.0.0_x64-setup.exe. Installs to %LOCALAPPDATA%\NdudutPro with desktop shortcut.
- **macOS:** Open Ndudut-Pro-1.0.0.dmg and drag Ndudut Pro.app into /Applications.

2. System Requirements & Dependencies

Component	Minimum Requirement	Recommended Configuration
Operating System	Windows 10/11 (64-bit) or macOS 12+	Windows 11 64-bit / macOS Sonoma 14+
CPU & GPU	Quad-core Intel / AMD x64 or Apple Silicon M1+	8-core CPU or M-series; NVIDIA NVENC/CUDA, Intel QSV, or AMD AMF
RAM & Storage	8 GB RAM, 2.5 GB free disk space	16 GB+ RAM, 5 GB+ high-speed NVMe SSD
FFmpeg & AI Core	Required for muxing, audio extraction & tracking	Auto-provisioned via Install Dependencies on first Studio launch

3. Licensing & 40-Day Free Trial

- **License Key Activation:** Click the **Free / Trial** badge in the left navigation rail (or open **Settings** → **License**), click **Activate**, paste your AINDPR*... serial, and submit.
- **40-Day Free Trial:** Click **40-Day Trial** in the activation dialog. **Ndudut Video** is always free; **Ndudut Studio** unlocks with daily quotas (**7 Reframes/day**, **3 Viral Shorts/day**, **10 Transcriptions/day**) and a trial watermark.
- **7-Day Offline Grace:** Activated machines work completely offline for up to 7 consecutive days before requiring check-in.
- **Floating License Servers:** Organizations using centralized license servers can enter @HOST or PORT@HOST (e.g. @REMOTE).
- **Deactivation:** Open **Settings** → **License** and click **Deactivate** to release the license seat for another machine.

4. Core Workflows

Universal Media Downloader (Video Tab)

1. Paste URL: Paste a link from 1,000+ sites. | **2. Mode:** Pick Video, Audio, GIF, HQ Edit, Proxy (720p), or Clipper. | **3. Download:** Save or send directly to Studio.

AI Smart Face Reframing (Studio → Reframe)

1. Import: Drop 16:9 video(s) into Studio Reframe. | **2. Configure:** Pick 9:16/1:1/4:5, Single or Split (2–4 speakers), sensitivity & SafeZone. | **3. Export:** Click **Generate Reframe**.

AI Viral Shorts Generation (Studio → Viral)

1. Detect: Switch to **Viral** in Studio, drop video, and click **Detect Viral Moments**. | **2. Trim & Style:** Adjust waveform bounds, karaoke captions & hooks. | **3. Render:** Click **Render Selected**.

Offline Transcription & Subtitle Editor (Studio → Transcribe)

1. Transcribe: Switch to **Transcribe** in Studio, drop video/audio, and click **Transcribe Media**. | **2. Edit & Export:** Review Standard/Verbatim views and export SRT/VTT/ASS/TXT.

5. Support & Documentation

- **In-App Guide:** Click **Guide** in the navigation rail | **Docs:** aescripts.com/ndudut-pro#documentation | **Support:** aescripts.com/contact/